


GO! Contemporary Cabin Quilt

finished size 40¼" x 40¼"
finished block size 5¼" x 5¼"



GO!® DIES USED

- Strip Cutter-2¼" (55053)

FABRIC REQUIREMENTS

- Fabric 1—1¼ yards fabric for blocks and binding
- Fabric 2—1 yard fabric for blocks and border
- Fabric 3—¼ yard fabric for blocks

- Backing Fabric—2½ yards
- Batting—46" square

CUTTING DIRECTIONS

Fabric 1:

- Cut 3—5¼" strips across width of fabric (WOF) for blocks, lay on Strip Cutter-2¼" perpendicular to blades and sub cut 49, 2¼" x 5¼" rectangles
- Cut 3—4" strips across WOF for blocks, lay on Strip Cutter-2¼" perpendicular to blades and sub cut 49, 2¼" x 4" rectangles
- Cut 5—2¼" strips across WOF for binding





Fabric 2:

- Cut 3—4" strips across WOF for blocks, lay on Strip Cutter-2¼" perpendicular to blades and sub cut 49, 2¼" x 4" rectangles
- Cut 4—2¼" strips across WOF for border
- Cut 3—2¼" strips across WOF for blocks, lay on Strip Cutter-2¼" perpendicular to blades and sub cut 49, 2¼" squares

Fabric 3:

- Cut 4—2¼" strips across WOF for blocks, lay on Strip Cutter-2¼" perpendicular to blades and sub cut 53, 2¼" squares

SEWING DIRECTIONS

1. Layout one, 2¼" Fabric #2 square and one, 2¼" Fabric #3 square. Pin and sew together. Press seams toward darker fabric. Make 49 combined units. 
2. Pin and sew one, 2¼" x 4" Fabric #2 rectangle to top of combined unit. Press seam toward rectangle. Make 49 expanded units. 
3. Pin and sew one, 2¼" x 4" Fabric #1 rectangle to side of expanded unit. Press seam toward Fabric #1 rectangle. Make 49. 
4. Pin and sew one, 2¼" x 5¼" Fabric #1 rectangle to top of pieced unit to complete block. Press seam toward rectangle just added. Make 49 blocks. 
5. Carefully layout blocks according to diagram.
6. Pin and sew rows together. Press seams of alternating rows in opposite directions.
7. Add 2¼" Fabric #2 border strips to sides of quilt center. Press seams toward border.
8. Add 2¼" Fabric #3 squares to each end of remaining two Fabric #2 border strips. Press seams toward border strips.
9. Add combined border strips to top of and bottom of quilt center. Press seams toward border.

QUILTING AND FINISHING

1. Layer batting between quilt top and backing.
2. Pin or baste layers together.
3. Machine quilt with an all-over design.
4. Add binding, mitring corners.